# Release Notes

**Product:** ADIC Management Console 4.3.2 with Library Management Console 1.3.1

Date: June 2005

#### Contents

# Page Topic Purpose of this Release System Requirements Compatibility Matrix Known Issues Resolved Issues Documentation

#### Purpose of this Release

This release adds several new features and enhancements that extend the capabilities of the ADIC Management Console (AMC). These release notes list corrections to problems that were encountered in previous releases of the AMC. Visit <a href="https://www.adic.com">www.adic.com</a> for additional information about the AMC and previous releases.

#### **New Features**

These features and enhancements are new to this release of the AMC software:

- The ability to retrieve the drive dump through the SNC
- LTO-3 support
- Ability to download the command flow logs on the SNC 5100
- SDLT 600 support
- i3.1 i2000 LMC Support (AMC 4.3.2 with LMC 1.3.1 only)



6-00274-13 Rev A

# System Requirements

The operating systems identified here are able to support the installation of AMC 4.3.2 server and SAN manager remote client.

| Operating Systems   |   |  |
|---------------------|---|--|
| Microsoft® Windows® | Windows 2000 (SP4 or later), Windows 2003, Window XP (SP2 or later) |  |
| HP-UX®              | HP-UX 11i or later  |  |
| Linux               | RedHat Enterprise Linux 3.0 or Advanced Server 2.1                  |  |
| Solaris™            | Solaris 9.0   |  |
| AIX®                | AIX 5.3   |  |

## **Compatibility Matrix**

The AMC 4.3.2 is compatible with the latest firmware versions of the ADIC Storage Network Controller (SNC) and storage products listed below.

| ADIC Product                                 | SNC      |
|--|----------|
| Scalar 24                                    | SNC 4000 |
| Scalar 100                                   | SNC 6101 |
| Scalar 1000                                  | SNC 5100 |
| Scalar 10K                                   | SNC 5100 |
| Scalar i2000 (AMC 4.3.2 with LMC 1.3.1 only) | SNC 6404 |
| Pathlight VX                                 | SNC 6404 |

© June 2005, ADIC

#### **Known Issues**

Known issues in this release of AMC are as follows:

| Change<br>Request<br>Number | Description   | Workaround |
|-----------------------------|---|------------|
| 12295                       | Currently there is no way to refresh the values in an i2000 library when a change occurs.   | N/A        |
| 20697                       | The AMC reports that a device is responding after a heartbeat check to the SNC states that the device is not connected.               | N/A        |
| 31028                       | The AMC inconsistently displays the Attention Window when an SNC is restarted; sometimes the window appears, other times it does not. | N/A        |
| 40447                       | The Fibre Channel Speed Config value=Auto setting reverts back to Auto after setting the value to disable.                            | N/A        |

#### Resolved Issues

This release of the ADIC Management Console 4.3.2 resolved the following issues. This table also shows cumulative information for previously released versions.

| Change<br>Request<br>Number | Description  |  |  |
|-----------------------------|--|--|--|
|                             | Version 4.3.2  |  |  |
| 43188                       | Firmware upgrade completes but the AMC locks up afterward.   |  |  |
| Version 4.3.1               |  |  |  |
| N/A                         | No new resolved issues. This is a production release to bundle the AMC 4.3.1 with the LMC 1.3 to support the Scalar i2000.   |  |  |
|                             | Version 4.3  |  |  |
| 13163                       | Create an automatic prompt for user login after connecting to server.  |  |  |
| 15441                       | All text saves now to an OS-specific suffix (such as .txt for Windows).  |  |  |
| 17611                       | After a Set Event Trap Threshold option within AMC has been changed (from any value to any value), the Event Logs are no longer viewable.  |  |  |
| 20839                       | Start IP Address and End IP Address ranges allow incorrect input in discovery segment.   |  |  |
| 20961                       | Rediscovery of Segments not working correctly. If you reduce the number of devices in a "discovery configuration", (which was used at the time of logon to AMC) and then rediscover the segment and re-logon, all the devices (previously present) that were removed from the discovery configuration are still present under AMC. |  |  |

© June 2005, ADIC 3

| Change<br>Request<br>Number | Description  |
|-----------------------------|--|
| 21599                       | The update drive/medium changer firmware screen defaults to ".bin" instead of ".lif".  |
| 22683                       | The recipient e-mail address information is added to the policy when either the "x" or the "close - Alt F4 option under the icon" is used. |
| 29224                       | It is not possible to change the SCSI channel to Target mode, but the AMC will allow the user to set the mode to Target and continue.      |
| 29603                       | The handling of first discovered SAN appliance inconsistently requires the user to re-login to the AMC for the appliance to be displayed.  |
| 29702                       | The Update Changer Firmware window disappears and the Client application locks up.   |
| 31136                       | The AMC SAN Client "Discover Appliance" fails when given a host name rather than dotted-decimal IP address.                                |
| 32357                       | The "x" button in the top right corner of a window (closing a window) causes SCSI parameters to be updated.                                |
| 34225                       | The AMC doesn't show drive/library firmware changes unless the AMC is restarted.   |
| 34773                       | Updating the Library Firmware through the SNC via the AMC is not functional.   |
| 35371                       | Uptime of libraries (i2K, PVX) are not displayed.  |
| 39417                       | Discovery parameters shown on the server console are confusing to user.  |

## Documentation

The following supporting documents are currently available for AMC:

| Document Number | Document Title                       |
|-----------------|--------------------------------------|
| 6-00064-06      | ADIC Management Console User's Guide |

4 © June 2005, ADIC